

Review All Permissions

Armor Knowledge Base

Topics Discussed

- [Security Permissions](#)
- [Marketplace Permissions](#)
- [Infrastructure Permissions](#)
- [Support Permissions](#)
- [Account Permissions](#)
- [General Permissions](#)

In the Armor Management Portal (AMP), permissions allow you to control the way your users access their AMP account.

There are many shared permissions between **Armor Complete** and **Armor Anywhere**. As a result, this document applies to both **Armor Complete** and **Armor Anywhere** users.

Review the **Product compatibility** column for product-specific permissions.



In the **Roles and Permissions** screen, you may see permissions that only apply to **Armor Complete** or **Armor Anywhere** users. Your roles will not malfunction if you include a permission for a different product into your role.

Security Permissions

Screen	Permission	Description	Product compatibility
Security Health Dashboards <ul style="list-style-type: none">• Health Overview (landing screen)• Protection• Detection• Response• Security Incidents	Read Dashboard Statistics	This permission allows you to view the data that populates the security dashboards.	<ul style="list-style-type: none">• Armor Complete• Armor Anywhere
Malware Protection	Read AVAM	This permission allows you to view antivirus and anti-malware (malware protection) details for each virtual machine.	<ul style="list-style-type: none">• Armor Complete• Armor Anywhere
Malware Protection	Read Trend Manual Scan	This permission allows you to view which virtual machines are eligible for a manual scan.	<ul style="list-style-type: none">• Armor Complete• Armor Anywhere
Malware Protection	Writer Trend Manual Scan	This permission allows you to start a manual scan for a virtual machine.	<ul style="list-style-type: none">• Armor Complete• Armor Anywhere
FIM	Read FIM	This permission allows you to view file integrity details for each virtual machine.	<ul style="list-style-type: none">• Armor Complete• Armor Anywhere

Patching	Read OS Packages	This permission allows you to view details OS patching details for each virtual machine.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Intrusion Detection	Read IDS	This permission allows you to view intrusion detection data.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Read LogManagement	This permission allows you to view high-level information for log collection for each virtual machine, such as: <ul style="list-style-type: none"> • Date logs were last received • Average size of collected logs • Log Status 	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Write LogManagement	This permission allows you to update the log management service, specifically the permission to upgrade the log retention plan.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Read Log Management Plan Selection	This permission allows you to view additional log retention plans.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Write Log Management Plan Selection	This permission allows you to change log retention plans.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Delete Log Management	This permission allows you to delete a log source.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Read Log Endpoints	This permission allows you to view an endpoint.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Write Log Endpoints	This permission allows you to create an endpoint.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Delete Log Endpoints	This permission allows you to delete an endpoint.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Read Log Relays	This permission allows you to view a remote log source.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Log & Data Management	Write Log Relays	This permission allows you to create a remote log source.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere

Log & Data Management	Delete Log Relays	This permission allows you to delete a remote log source.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Vulnerability Scanning	Read Compliance	This permission allows you to view information for the vulnerability scanning add-on product information. Specifically, you will see the status of the add-on product.	<ul style="list-style-type: none"> • Armor Complete
Vulnerability Scanning	Write Compliance	This permission allows you to upgrade, downgrade, or delete the vulnerability scanning add-on product.	<ul style="list-style-type: none"> • Armor Complete
Vulnerability Scanning	View Vulnerability Scans	This permission allows you to view the data for a vulnerability scanning report, via a downloaded report or within AMP.	<ul style="list-style-type: none"> • Armor Anywhere
Dynamic Threat Blocking	Read Dynamic Threat Blocking Rule(s)	This permission allows you to view IP rules that have been created.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Dynamic Threat Blocking	Write Dynamic Threat Blocking Rule(s)	This permission allows you to create and delete an IP rule (whitelist or blacklist).	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Dynamic Threat Blocking	Write Dynamic Threat Blocking Rule Never Expire IP	This permission allows you to create an IP rule (whitelist or blacklist) without an expiration date.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Dynamic Threat Blocking	Read Dynamic Threat Blocking(s)	This permission allows you to perform an IP lookup. Additionally, this permission allows you to view other IP lookups that have taken place in your account.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Firewall	Read Firewall	This permission allows you to view details for firewall rules for each virtual machine.	<ul style="list-style-type: none"> • Armor Complete
Firewall	Write Firewall	This permission allows you to add, update, or delete firewall rules.	<ul style="list-style-type: none"> • Armor Complete
Security Incidents	Read Dashboard Statistics	This permission allows you to view the data that populates the security dashboards, which includes open or pending security incidents.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere

Marketplace Permissions

Screen	Permission	Description	Product compatibility
Marketplace	Read Product Catalog	This permission allows you to view available add-on products. You must have this permission enabled in your account in order to view purchased services and also to order new services in AMP.	<ul style="list-style-type: none"> • Armor Complete
Marketplace and My Products	View Subscriptions	This permission allows you to view subscription-based add-on products in the My Products screen of the User Details screen.	<ul style="list-style-type: none"> • Armor Complete

Marketplace (and My Products)	Write Subscriptions	This permission allows you to view the Armor Marketplace, as well as add and cancel subscription-based add-on products. Specifically, you can add the subscription in the Armor Marketplace, and then cancel the subscription in the My Products screen of the User Details screen.	<ul style="list-style-type: none"> • Armor Complete
--------------------------------------	---------------------	--	--

Infrastructure Permissions

Screen	Permission	Description	Product compatibility
Workloads	Read Workload(s)	This permission allows you to view high-level data for workloads, such as <ul style="list-style-type: none"> • the associated data center • the number of tiers within the workload • the number of virtual machines within the workload 	<ul style="list-style-type: none"> • Armor Complete
Workloads	Write Workload	This permission allows you to create, update, and remove workloads and tiers.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Read Virtual Machine Stats	This permission allows you to view usage data for a virtual data. This data is displayed in a line graph.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Read Virtual Machine(s)	This permission allows you to view data for a virtual machine, such as <ul style="list-style-type: none"> • Operating system • Size • Corresponding workload • Status 	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Write Virtual Machine	This permission allows you to update and remove virtual machines.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Virtual Machines	Read Orders	This permission allows you to view data related to your virtual machine purchase.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Write Orders	This permission allows you to purchase a virtual machine.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Scale Virtual Machine	This permission allows you upgrade or downgrade (resize) the size of a virtual machine.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Read Location(s)	This permission allows you to view a list of available Armor data centers when you manage your virtual machines.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Read Virtual Data Centers	This permission allows you to view the list of virtual environments in your account.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Read Server Replication	This permission allows you to view high-level data for the server replication (disaster recovery) add-on product. Specifically, this permission allows you to view: <ul style="list-style-type: none"> • The status of the add-on product (configuring, enabled, disabled) • The location of the primary data center • The location of the failover data center • The status of the replication 	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Write Server Replication	This permission allows you to order and cancel the server replication add-on product.	<ul style="list-style-type: none"> • Armor Complete

Virtual Machines	Read Tasks	This permission allows you to view pending tasks, such as a scheduled delete or downsize of a virtual machine.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Write Tasks	This permission allows you to schedule a delete or downsize of a virtual machine.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	Read Storage	This permission allows you to view disk and storage information for a virtual machine.	<ul style="list-style-type: none"> • Armor Complete
Virtual Machines	View Core License	This permission allows you to view the core license, which is necessary to download and install the Anywhere agent.	<ul style="list-style-type: none"> • Armor Anywhere
Virtual Machines	Read Utilization	This permission allows you to export the usage for your virtual machine.	<ul style="list-style-type: none"> • Armor Anywhere
IP Addresses	Read Network IP	This permission allows you to view data for unassigned and assigned public and private IP addresses	<ul style="list-style-type: none"> • Armor Complete
IP Addresses	Write Network IP	This permission allows you to update an IP address, such as: <ul style="list-style-type: none"> • Assign an IP addresses • Unassign an IP addresses • Delete IP address • Request a new public IP address 	<ul style="list-style-type: none"> • Armor Complete
IP Addresses	Read Network NAT	This permission allows you to view DNAT assignments.	<ul style="list-style-type: none"> • Armor Complete
IP Addresses	Write Network NAT	This permission allows you to add and remove DNAT assignments.	<ul style="list-style-type: none"> • Armor Complete
L2L VPN	Read Network L2L	This permission allows you to view high-level data for your L2L network tunnels.	<ul style="list-style-type: none"> • Armor Complete
L2L VPN	Write Network L2L	This permission allows you to add, update, and remove L2L tunnels.	<ul style="list-style-type: none"> • Armor Complete
SSL/VPN	Read SSL VPN Devices and Users	This permission allows you to view the status of your users' SSL VPN client.	<ul style="list-style-type: none"> • Armor Complete
SSL/VPN	Write SSL VPN Devices and User	This permission allows you to enable your users the ability to download and install the SSL VPN client.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Commit Advanced Backup Restore	This permission allows you to commit a snapshot after the restoration is complete.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Create Advanced Backup Policy	This permission allows you to create a new policy.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Read Advanced Backup	This permission allows you to view the Advanced Backup screen.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Read Advanced Backup Policy	This permission allows you to view policy information and details.	<ul style="list-style-type: none"> • Armor Complete

Advanced Backup	Read Advanced Backup Snapshots	This permission allows you to view a list of snapshots (backups) for a virtual machine.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Read Advanced Backup Vms	This permission allows you to view the virtual machines that are subscribed to Advanced Backup.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Refreshed Advanced Backup Snapshots	This permission allows you to refresh the current list of available snapshots (backups) for a virtual machine.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Remove Advanced Backup	This permission allows you to remove Advanced Backup from a virtual machine.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Request Advanced Backup Restore	This permission allows you to initiate a restoration of a snapshot (backup).	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Update Advanced Backup Policy	This permission allows you to update the configurations of a policy.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Write Advanced Backup	This permission allows you to create a policy.	<ul style="list-style-type: none"> • Armor Complete
Advanced Backup	Read Advanced Backup Plans	This permission allows you to view a list of policies.	<ul style="list-style-type: none"> • Armor Complete

Support Permissions

Screen	Permission	Description	Product compatibility
Tickets	Read Ticket(s)	This permission allows you to view support tickets listed in the View Archived Tickets section.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Tickets	Write Ticket(s)	This permission allows you to create, edit, respond, and share a ticket.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Tickets	Read Ticket Group (s)	This permission allows you to view and follow a support ticket, as well as access the Organization features of the ticket.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Tickets	Write Ticket Group (s)	This permission allows you to create and follow a support ticket, as well as access the Organization features of the ticket.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere

Account Permissions

Screen	Permission	Description	Product compatibility
--------	------------	-------------	-----------------------

Overview (Account screen)	Read Identity	This permission allows you to view the account-level information, such as <ul style="list-style-type: none"> Account overview Armor contacts User profiles Roles and permissions 	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
Overview (Account screen)	Write Identity	This permission allows you to update account-level information, such as: <ul style="list-style-type: none"> Invite and remove users Create, update, and remove roles Assign and unassign roles to users Unlock a user after several failed login attempts 	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
Overview (Account screen)	Write Account	This permission allows you to update your company profile, such as the address.	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
User Detail	Update Personal Identity	This permission allows you to update your personal account information, such as your: <ul style="list-style-type: none"> Password Challenge Phrase Challenge Response 	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
Cloud Connections	Read Cloud Connections	This permission allows you to view public cloud accounts that have been synced with AMP.	<ul style="list-style-type: none"> Armor Anywhere
Cloud Connections	Write Cloud Connections	This permission allows you to add a new public cloud account to sync with AMP.	<ul style="list-style-type: none"> Armor Anywhere
User Detail	Read Notification (s)	This permission allows you to view the notification preferences for your users, such as a user's preference to receive an email regarding technical updates.	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
Invoices + Payments	View Invoices	This permission allows you to view current and previous invoices.	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
Payment Methods	Read Payment Information	This permission allows you to view current payment information, such as the primary payment method.	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
Payment Methods	Update Payment Information	This permission allows you to update the payment information, such as adding a new credit card or assigning a new primary payment method	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
API Keys (Users screen)	API Keys All Read	This permission allows you to view API keys that have been created.	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
API Keys (Users screen)	API Keys All Delete	This permission allows you to delete an API key.	<ul style="list-style-type: none"> Armor Complete Armor Anywhere
API Keys (Users screen)	API Keys Self Manange	This permission allows you to create an API key.	<ul style="list-style-type: none"> Armor Complete Armor Anywhere

Activity	View Account Activity	This permission allows you to view the account activity for your users.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Sub-Accounts	View Sub-Accounts	This permission allows you to view the Sub-Accounts screen	<ul style="list-style-type: none"> • Armor Anywhere
Sub-Accounts	Write Sub-Accounts	This permission allows you to create and update sub-accounts.	<ul style="list-style-type: none"> • Armor Anywhere

General Permissions

Screen	Permission	Description	Product Compatibility
Not applicable	Read Entity Metadata	This permission allows you to view optional notes and tags that have been added to various AMP resources, such as a note added to a virtual machine.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Not applicable	Write Entity Metadata	This permission allows you to add, update, and delete optional notes and tags to various AMP resource, such as adding a note to a virtual machine.	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere
Not applicable	Read Documentation	This permissions allows you to view documentation related to a particular product or screen, via the Help icon in the top right corner of the AMP screen (where applicable).	<ul style="list-style-type: none"> • Armor Complete • Armor Anywhere



Was this helpful? ^{*}

Your Rating: ☆☆☆☆☆

Results: ★★★★★ 13 rates

